

# HI\_SetColumnMasterEditable

## %HI\_GetColumnMasterEditable, %HI\_SetColumnMasterEditable functions

Function	<p>The <b>%HI_SetColumnMasterEditable</b> function disables to change a text in the column in the display of <a href="#">Browser</a> type (overloads the function <a href="#">%HI_SetEditEnable</a>) / cancels the overloading and enables to change the text in particular column as defined by the function <b>%HI_SetEditEnable</b> (<a href="#">control function</a>).</p> <p>The <b>%HI_GetColumnMasterEditable</b> function gets the current status of overloading that is defined by <b>%HI_SetColumnMasterEditable</b>.</p>						
Declaration	<pre>%HI_SetColumnMasterEditable(     INT in refId,     INT in col,     BOOL in bEnable )  BOOL %HI_GetColumnMasterEditable(     INT in refId,     INT in col )</pre>						
Parameters	<table><tr><td>refId</td><td>Reference to graphic object (<a href="#">reference variable</a>).</td></tr><tr><td>col</td><td>Column in Browser.</td></tr><tr><td>bEnable</td><td>@TRUE - enables the graphic object @FALSE - disables the graphic object</td></tr></table>	refId	Reference to graphic object ( <a href="#">reference variable</a> ).	col	Column in Browser.	bEnable	@TRUE - enables the graphic object @FALSE - disables the graphic object
refId	Reference to graphic object ( <a href="#">reference variable</a> ).						
col	Column in Browser.						
bEnable	@TRUE - enables the graphic object @FALSE - disables the graphic object						
Description	<p>The <b>%HI_SetColumnMasterEditable</b> function disables to change a text in the column in the display of <a href="#">Browser</a> type - the parameter <i>refId</i> defines the name of the reference variable for Browser. When <i>bEnable</i> parameter is @FALSE, it overloads the <b>%HI_SetEditEnable</b> function (disables its functionality).</p> <p>The <b>%HI_GetColumnMasterEditable</b> function gets the current status of overloading of editing which is set by <b>%HI_SetColumnMasterEditable</b>. The return value @TRUE does not mean that the column can be edited, but the column fields are controlled by <b>%HI_SetEditEnable</b>. @FALSE means the functionality of <b>%HI_SetEditEnable</b> function is disabled and the text in the column object cannot be changed.</p> <p>The behavior of Master functions is described in the chapter Master functions.</p>						
Example	<pre>ENTRY OnLogOn(IN TEXT _userName, IN BOOL _bLogOn)     IF _bLogOn THEN          ;when a user is logged on, a text in column can be edited         %HI_SetColumnMasterEditable(_Text,@TRUE)     ELSE          ;when a user is logged off, the access to a text in column is disabled         %HI_SetColumnMasterEditable(_Text,@FALSE)     ENDIF END OnLogOn</pre>						
Note	This function is also in <a href="#">%HIX_ version</a> .						



**Related pages:**

[Graphic object manipulation functions](#)  
[Function arguments - types](#)