

Set up system and application help

Help is set on 2 levels:

1. On the server side
2. On the side of client processes

Set up system and application help on the server side

The process [D2000 Server](#) reads the following parameters from the system registry during its start. Values are adjusted using the process [D2000 Application Manager](#) (D2Smc.exe).

Parameter	Possible Values	Parameter Meaning
SrvApplHelpType	HelpFileChm	Selection of Application Help Types - NoHelp, HelpFileChm, HelpWebServerConfluence, HelpWebServerHtml, HelpSharedDir, HelpLocalAppDir, HelpLocalAnyPath
SrvApplHelpPath		Set the location of the help by type SrvApplHelpType.
SrvApplHelpMainPage		Default application help page. It is entered in the form: "html/main_page.htm" (mandatory form for type HelpFileChm). F for html helps "main_page" is enough.
SrvD2000HelpType	HelpWebIPS	Selection of help types for D2000 - HelpWebIPS, HelpWebServerHtml, HelpSharedDir, HelpLocalD2000Dir, HelpLocalAnyPath
SrvD2000HelpPath	https://doc.ipesoft.com/label/D2DOCV	Set the location of the help by type SrvD2000HelpType.

The setup consists of 2 parts:

1. Enter the keyword in SrvD2000HelpType
2. Defining the location of the help in SrvD2000HelpPath. Placements are somewhat relative, and the final path is completed according to the rules described below. The deduction depends on the type of help given by the keyword and is described in the table. The calculated path then adds references to specific help stalls. Some routes are predefined and can not be changed. Reasonable use of "relative" paths is the ability to use multilingual help depending on which language the user uses on his console and helps for different versions.

Key Word	Meaning	SrvD2000HelpPath - Help location settings
HelpWebIPS	Ipesoft webserver (Confluence). Current help available on the website of Ipesoft Ltd. It is continuously updated.	<p>The path is defined by the text "https://doc.ipesoft.com/label/D2DOCV" and cannot be changed. The following is added to the final destination path as follows: the D2000 version is added to the path, e.g.: 11 and the help language e.g.: SK.</p> <p>Example of final location: https://doc.ipesoft.com/label/D2DOCV22SK/</p>
HelpWebServerHtml	Web server (HTML). Help is available through some websites.	<p>The path leads to an Internet address. It must be entered.</p> <p>E.g.: https://MyPages/help</p> <p>The physical location is completed as follows: the help language is added to the path, e.g.: SK + keyword label</p> <p>Example of the final location: https://MyPages/help/SK/label/</p>
HelpSharedDir	Shared directory (HTML). Help directory located on a network drive common to multiple D2000 consoles that have access to it.	<p>The path points to any location on the network drive. It must be entered.</p> <p>E.g.: S:\D2000_HELP.</p> <p>The physical location is completed as follows: the help language is added to the path, e.g.: SK + keyword label</p> <p>Example of final location: S:\D2000_HELP\SK\label\...</p>

HelpLocalD2000Dir	HELP installation directory D2000 (HTML)	<p>The path points to the location referenced by the D2000 installation and cannot be changed.</p> <p>E.g.: C:\D2000\D2000_V11.2.57\D2000_EXE\HELP.</p> <p>The physical location is completed as follows: the help language is added to the path, e.g.: SK + keyword label</p> <p>Example of the final location: C:\D2000\D2000_V11.2.57\D2000_EXE\HELP\SK\label\...</p>
HelpLocalAnyPath	Local Directory (HTML). A help directory located on a local or network drive that can be accessed by the D2000 console.	<p>The path points to any location on the local disk. It must be entered.</p> <p>E.g.: C:\D2000_HELP.</p> <p>The physical location is completed as follows: the help language is added to the path, e.g.: SK + keyword label</p> <p>Example of final location: C:\D2000_HELP\SK\label\...</p>

Language of the Help

When the help is opened, a language mutation is selected depending on which language the user uses for the client process (HI, CNF, ...) The following are allowed:

SK - for Slovak and Czech language

EN - for other languages

Set up application help on the server side

The setup consists of 3 parts:

1. Enter the keyword in SrvApplHelpType
2. Defining the location of the help in SrvApplHelpType. Placements are somewhat relative, and the final path is added when you open help. The reason is the ability to use multilingual helps and helps for different versions. Meaning depends on the type of help given by the keyword and is described in the table. Some routes are predefined and can not be changed.
3. Default application help page in SrvApplHelpMainPage.

Keyword	Meaning	SrvApplHelpPath - Help location settings
NoHelp	Without help	Not specified
HelpFileChm	HELP application directory (CHM). It uses chm files as help.	<p>The path points to the location referenced by the D2000 application and cannot be changed.</p> <p>E.g.: C:\D2000\D2000_V11.2.57\D2000_APP\Demo\HELP.</p>
HelpWebServerConfluence	Web server (Confluence). Help available through any website created in Confluence	The path leads to an Internet address. It must be entered. The physical location is ultimately required to comply with Confluence rules
HelpWebServerHtml	Web server (HTML). Help is available through some websites.	<p>The path leads to an Internet address. It must be entered.</p> <p>E.g.: https://MyPages/help</p> <p>The physical location is completed as follows: the help language is added to the path, e.g.: SK + keyword label</p> <p>Example of the final location: https://MyPages/help/SK\label/</p>
HelpSharedDir	Shared directory (HTML). Help directory located on a network drive common to multiple D2000 consoles that have access to it.	<p>The path points to any location on the network drive. It must be entered.</p> <p>E.g.: S:\MY_HELP.</p> <p>The physical location is completed as follows: the help language is added to the path, e.g.: SK + keyword label</p> <p>Example of final location: S:\MY_HELP\SK\label\ ...</p>

HelpLocalAp pIDir	HELP application directory (HTML)	<p>The path points to the location referenced by the D2000 application and cannot be changed.</p> <p>E.g.: C:\D2000\D2000_V11.2.57\D2000_APP\Demo\HELP.</p> <p>The physical location is completed as follows: the help language is added to the path, eg: SK + keyword label</p> <p>Example of final location: C:\D2000\D2000_V11.2.57\D2000_APP\Demo\HELP\SK\label\.....</p>
HelpLocalAn yPath	Local Directory (HTML) A help directory located on a local or network drive that can be accessed by the D2000 console.	<p>The path points to any location on the local disk. It must be entered.</p> <p>E.g.: C:\MY_HELP.</p> <p>The physical location is completed as follows: the help language is added to the path, e.g.: SK + keyword label</p> <p>Example of final placement: C:\MY_HELP\SK\label\...</p>

Language of the Help


When the help is opened, a language mutation is selected depending on which language the user uses for the client process (HI, CNF, ...) The following are allowed:

SK - for Slovak and Czech language

EN - for other languages


Set up system and application help on the side of client processes

It is entered by selecting the activity in the submenu "Help" of the client process, e.g. in HI:



Set up system help on the side of client processes


The settings window at the top contains settings on the server side and at the bottom on the client side.



Location	Meaning	Path - Set the location of help
D2000 server setting	Setting according to the D2000 server	The location is taken from the settings on the server
Ipesoft webserver (Confluence).	Current help available on the website of Ipesoft Ltd. It is continuously updated.	<p>The path is defined by the text "https://doc.ipesoft.com/label/D2DOCV" and cannot be changed. The following is added to the final destination path as follows: the D2000 version is added to the path, e.g.: 11 and the help language e.g.: SK.</p> <p>Example of final location: https://doc.ipesoft.com/label/D2DOCV22SK/</p>
Web server (HTML)	Help is available through some websites.	<p>The path leads to an Internet address. It must be entered.</p> <p>E.g.: https://MyPages/help</p> <p>The physical location is completed as follows: the help language is added to the path, e.g.: SK + keyword label</p> <p>Example of the final location: https://MyPages/help/SK/label/</p>
Shared directory (HTML).	Help directory located on a network drive common to multiple D2000 consoles that have access to it.	<p>The path points to any location on the network drive. It must be entered.</p> <p>Eg: S:\D2000_HELP.</p> <p>The physical location is completed as follows: the help language is added to the path, e.g.: SK + keyword label</p> <p>Example of final location: S:\D2000_HELP\SK\label\...</p>
HELP installation directory D2000 (HTML)	HELP installation directory D2000 (HTML)	<p>The path points to the location referenced by the D2000 installation and cannot be changed.</p> <p>E.g.: C:\D2000\D2000_V11.2.57\D2000_EXE\HELP.</p> <p>The physical location is completed as follows: the help language is added to the path, e.g.: SK + keyword label</p> <p>Example of the final location: C:\D2000\D2000_V11.2.57\D2000_EXE\HELP\SK\label\...</p>
Local directory (HTML)	Help directory located on a local or network drive that can be accessed by the D2000 console.	<p>The path points to any location on the local disk. It must be entered.</p> <p>E.g.: C:\D2000_HELP.</p> <p>The physical location is completed as follows: the help language is added to the path, e.g.: SK + keyword label</p> <p>Example of final location: C:\D2000_HELP\SK\label\...</p>

Set up application help on the side of client processes

The settings window at the top contains settings on the server side and at the bottom on the client side



The dialog box is titled "Set the application help location". It contains two main sections: "Server" and "Client".

Server section:

- Location:** A text box containing "HELP directory of application (CHM)".
- Cesta:** A text box containing "C:\D2000\D2000U_APP\UnicodeLH\Help".

Client section:

- Location:** A dropdown menu with "No Help" selected.
- Cesta:** An empty text box with a browse button (three dots) to its right.

At the bottom, there are two buttons: "Nastav" (Next) and "Zatvor" (Close).

Location	Meaning	Path - Set the location of the help
D2000 server setting	Setting according to the D2000 server	The location is taken from the settings on the server
Without help	No help. The application does not provide help	Not specified
HELP application directory (CHM)	It uses chm files as help.	The path points to the location referenced by the D2000 application and cannot be changed. E.g.: C:\D2000\D2000_V11.2.57\D2000_APP\Demo\HELP.
Web server (Confluence)	Help is available through any website created in Confluence	The path leads to an Internet address. It must be entered. The physical location is ultimately required to comply with Confluence rules
Web server (HTML)	Help is available through some websites.	The path leads to an Internet address. It must be entered. E.g.: https://MyPages/help The physical location is completed as follows: the help language is added to the path, e.g.: SK + keyword label Example of the final location: https://MyPages/help/SK/label/
Shared directory (HTML)	Help directory located on a network drive common to multiple D2000 consoles that have access to it.	The path points to any location on the network drive. It must be entered. E.g.: S:\MY_HELP The physical location is completed as follows: the help language is added to the path, e.g.: SK + keyword label Example of final location: S:\MY_HELP\SK\label\ ...
HELP application directory (HTML)	HELP application directory (HTML)	The path points to the location referenced by the D2000 application and cannot be changed. E.g.: C:\D2000\D2000_V11.2.57\D2000_APP\Demo\HELP. The physical location is completed as follows: the help language is added to the path, e.g.: SK + keyword label Example of final location: C:\D2000\D2000_V11.2.57\D2000_APP\Demo\HELP\SK\label\...
Local directory (HTML)	Help directory located on a local or network drive that can be accessed by the D2000 console.	The path points to any location on the local disk. It must be entered. E.g.: C:\MY_HELP. The physical location is completed as follows: the help language is added to the path, e.g.: SK + keyword label Example of final placement: C:\MY_HELP\SK\label\ ...