

XML_ImportD2ObjFromDocument

%XML_ImportD2ObjFromDocument function

Function	The function imports an object, represented by an XML document, to configuration.														
Declaration	<pre>BOOL %XML_ImportD2ObjFromDocument(INT in document, TEXT in importSettings INT in expSubDirMode)</pre>														
Parameters	<table><tr><td>document</td><td>Handle to the XML document.</td></tr><tr><td>importSettings</td><td>XML Import settings (optional parameter) in form [setting={on/off} [setting={on/off} [...]]].</td></tr><tr><td>expSubDirMode</td><td>Mode (optional parameter) that defines setting the attribute "Export subdirectory" of object after finished import.</td></tr></table>			document	Handle to the XML document.	importSettings	XML Import settings (optional parameter) in form [setting={on/off} [setting={on/off} [...]]].	expSubDirMode	Mode (optional parameter) that defines setting the attribute "Export subdirectory" of object after finished import.						
document	Handle to the XML document.														
importSettings	XML Import settings (optional parameter) in form [setting={on/off} [setting={on/off} [...]]].														
expSubDirMode	Mode (optional parameter) that defines setting the attribute "Export subdirectory" of object after finished import.														
Return value	@TRUE - the function was done successfully @FALSE - the function failed														
Description	<p>The function imports the object, represented by an XML document, to configuration. It can not be applied on the object which has been gotten by the %XML_OpenDocument function, if the object (xml file) contains the binary data (bin files).</p> <p>Constance for the parameter expSubDirMode:</p> <table><tr><th>Numerical value</th><th>Constant</th><th>Description</th></tr><tr><td>0</td><td>@SDM_KEEP_VALUE</td><td>Keep value of attribute as it was originally set in the configuration of object.</td></tr><tr><td>1</td><td>@SDM_DELETE</td><td>Delete value of attribute in the configuration of object.</td></tr><tr><td>3</td><td>@SDM_SET_SOURCE</td><td>Set value of attribute as it is defined in the imported XML data.</td></tr></table>			Numerical value	Constant	Description	0	@SDM_KEEP_VALUE	Keep value of attribute as it was originally set in the configuration of object.	1	@SDM_DELETE	Delete value of attribute in the configuration of object.	3	@SDM_SET_SOURCE	Set value of attribute as it is defined in the imported XML data.
Numerical value	Constant	Description													
0	@SDM_KEEP_VALUE	Keep value of attribute as it was originally set in the configuration of object.													
1	@SDM_DELETE	Delete value of attribute in the configuration of object.													
3	@SDM_SET_SOURCE	Set value of attribute as it is defined in the imported XML data.													
Example	<pre>BOOL _ok INT _doc _ok := %XML_ImportD2ObjFromDocument(_doc)</pre> <pre>BOOL _ok INT _doc _ok := %XML_ImportD2ObjFromDocument(_doc, "uid_strict=off uid_usexml=on")</pre>														
Note	<p>Error description can be called by means of ESL function %XML_GetLastErrorMessage. Error code can be called by means of ESL function %XML_GetLastErrorCode. The code "-11" means that XML Import failed because other one had been already running.</p>														



Related pages:

[XML file manipulation functions](#)
[Function arguments - types](#)