Printing Graphic Information Windows (HI)

Printing graphic information windows

To print use the following way:

- 1. Open the graphic information window (picture, graph) to print on the desktop of the process D2000 HI.
- Click the **Print** button from the Main toolbar (or press CTRL+P). Opened dialog box allows to define required print parameters.
 Define the print parameters according to your needs and click the **Print** button.

\\srvipsw1\PRN11 HPLJ2015dn \\srvipsw1\PRN11 HPLJ2015dn					
{Date}	✓ {Name of 1. object}	▼ {User}			
	D.SYS.Kernel	SystemD2000			
	D.STO.Ronde				
	12 000 000				
	11 500 000-				
		<u></u>			
	1 500 000				
	5 COC COC 5 COC AM 5 COC AM 2 22/2010	2:20 PM 2/23/2010			
	- Mana	2/23/2010			
	1.CPU load 1.CPU load 2.Socrase menory ba 4.Fee memory ba				
	2. Pres memory size 3. Number d'reguess for 20000 Servier 3. Performed reguess for 20000 Servier 3. Performed reguess for 20000 Servier 3. Performed reguess for configuration doublese				
	2. Participand units regulate for configuration disables 2. Parading with a regulate for big disables 2. Parading with a regulate for big disables 2. Participand in the regulate for big disables				
	2000 EHis, VS 00 000				
{Product}	✓ {Name of 2. object}	•			
		Printer			
- Output compo	sition Size: Description for graph				
1. D.SYS.Ke	mel 🔹 🔹 🚺	Table			
2.	• •				
3.	· · · · · · · · · · · · · · · · · · ·				
4.					
	<u>P</u> rint				

Description of the "Print" dialog box

Print preview

The large area in the top part of dialog box that shows the print output on page.

Header and footer

Input fields to enter parameters of header and footer are placed above and below the print preview. The input fields contain the menu of some predefined key words that will be replaced with current data during print. Meaning of these keywords is shown in the following table. Keywords are replaced with corresponding data only if the the text in particular input field does not contain other symbols.

Key word	Meaning
{Appl. Descrip}	Application descriptive text
{Date}	Date
{Date and Time}	Date and time
{Time and Date}	Time and date
{Product}	Product name
{Product and Logo}	Product name + Ipesoft's logo
{User}	Logged on user's name
{Name of 1. object}	Name of 1st window (2nd,)
{Description of 1. object}	Description of 1st window (2nd,)
{Name and description of 1. object}	Name and description of 1st window (2nd,)

Composition

Defines the maximum number of printed windows and their arrangement on page.

Orientation

Allows to select the page orientation - portrait or landscape.

Output composition

According to selected type of composition you can choose one of the opened windows or empty one. You can set the output size of each selected window and in case of pictures you can enable / disable the background printing.

For objects of *Graph* type, the input field **Edit** contains the name and description, defined in the graph configuration. The description may be modified and will be shown above the graph in the print preview area. A change is to be displayed in the print preview after clicking out of the input filed **Description**.

Depending on the type of the object you want to print, there will be displayed either the checkbox **Background** (for compositions, pictures) or the checkbox **Table** (for graphs).

Background - enable / disable printing the object background.

Table - 3 possible states of the checkbox:

Table - print all column of the table

Table - print the column containing the object names

Table - do not print the table

Printer

Printer and page setup.

Printer and page setup

Printer

It is selected from the list of output devices (printers) installed in the operating system.

Orientation

Select the page orientation - portrait or landscape. The parameter is synchronized with the parameter in the Print dialog box.

Margins

Set the margins that represent distances (in millimeters) of the printed graphic information window from the left, right, top and bottom margin of page - the L eft, Right, Top and Bottom input boxes. Click the Set margins button to confirm entered values of margins.

Properties

This option allows changing the local settings of printing for the selected printer, such as page layout, number of copies, print format and others. The parameters depend on a driver for given printer so the options, that they allow to set, can vary. The changed settings will be applied only for the current print and are not saved for the future use. After closing the **Print** dialog window or changing the printer, the defined settings are reset and the

printer has the default properties. The new settings do not influence the default print settings for the given printer.

Printer and parameters of page						
Printer and parameters of page						
\\\$RVIPSW1\PRN02 HPLJ2200 3p						
Orientation	Margins					
	Top 5					
• A	Left 5 192x279 5 Right					
○ A ⁵	Bottom 5 Set margins					
QK						

Note: The information concerning the report printing from HI desktop you can find in the topic Print the report on printer.