

# ERR\_NR\_TRANS\_EX - List of existing errors

The following table contains the list of existing errors returned by the local variable [\\_ERR\\_NR\\_TRANS\\_EX](#).

| Internal name                                                    | Value | Description                                                                         |
|------------------------------------------------------------------|-------|-------------------------------------------------------------------------------------|
| <b>Error codes during work with system objects</b>               |       |                                                                                     |
| OK                                                               | 0     | OK.                                                                                 |
| OBJECT_ALREADY_EXISTS                                            | 1     | Object already exists.                                                              |
| OBJECT_NOT_FOUND                                                 | 2     | Object does not exist.                                                              |
| INVALID_ACCESS                                                   | 3     | Insufficient access rights.                                                         |
| SHARED_ACCESS_ERROR                                              | 4     | Access error when trying to edit (object is being edited by other user).            |
| OBJECT_NOT_OPENED                                                | 5     | Object is not open.                                                                 |
| OBJECT_IS_USED                                                   | 6     | Object is used (when trying to delete it).                                          |
| INVALID_NAME                                                     | 7     | Invalid object name.                                                                |
| FATAL_ERROR                                                      | 8     | Fatal error.                                                                        |
| OBJECT_IS_READ_ONLY                                              | 9     | Object is read-only (when trying to edit or delete it).                             |
| OBJECT_HAS_CHILDREN                                              | 10    | Object has children (when trying to delete it).                                     |
| SAVE_REFERENCES_ERROR                                            | 11    | Incorrect object references.                                                        |
| LICENCE_LIMIT_OVERRUN                                            | 46    | Licence limit overrun (when trying to create a new object).                         |
| <b>Error codes for output control</b>                            |       |                                                                                     |
| MANUAL_CTRL_DISABLED                                             | 12    | Manual control disabled (when trying to set a value manually).                      |
| BAD_COMMAND                                                      | 13    | Bad command.                                                                        |
| COMMAND_NOT_ACCEPTED                                             | 14    | Illegal command.                                                                    |
| PROCESS_NOT_RUNNING                                              | 15    | Process for execution of the command is not running.                                |
| <b>Error codes for configuration of <a href="#">topology</a></b> |       |                                                                                     |
| CREATE_NEW_ERROR                                                 | 16    | Error during creation of a new object of <a href="#">Topology</a> type.             |
| BAD_PARENT                                                       | 17    | Object has another parent.                                                          |
| NAME_ALREADY_EXISTS                                              | 18    | Object with given name already exists - it is of other type.                        |
| BAD_CONNECT                                                      | 19    | Inappropriate control object for topological node of <a href="#">Terminal</a> type. |
| <b>Error codes for user's logins</b>                             |       |                                                                                     |
| USER_INVALID_ACCESS                                              | 20    | Invalid access rights.                                                              |
| LOGON_WRONG_PASSWORD                                             | 21    | Incorrect password. (version <= 12.2.65)                                            |
| LOGON_NAME_ERROR                                                 | 22    | Incorrect login name. (version <= 12.2.65)                                          |
| PASSWORD_EXPIRED                                                 | 23    | Password validity has expired.                                                      |

|                                                                                                                                           |    |                                                                                                                                                                                                                                                            |
|-------------------------------------------------------------------------------------------------------------------------------------------|----|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| USER_IS_DISABLED                                                                                                                          | 24 | User login is disabled.                                                                                                                                                                                                                                    |
| USER_EXPIR_TIME                                                                                                                           | 25 | Validity of user's account has expired.                                                                                                                                                                                                                    |
| LOGON_NAME_PASS<br>WORD_ERROR                                                                                                             | 54 | Incorrect name or password. (version >= 12.2.67)                                                                                                                                                                                                           |
| <b>Error codes for database backup</b>                                                                                                    |    |                                                                                                                                                                                                                                                            |
| DATABASE_NOT_VAL<br>ID                                                                                                                    | 26 | Database not valid.                                                                                                                                                                                                                                        |
| BACKUP_FAILED                                                                                                                             | 27 | Backup failed.                                                                                                                                                                                                                                             |
| OTHER_ERROR                                                                                                                               | 28 | Other error.                                                                                                                                                                                                                                               |
| PATH_NOT_COMPLE<br>TE                                                                                                                     | 29 | Path not complete.                                                                                                                                                                                                                                         |
| <b>Error codes for access to database ( <a href="#">D2000 Archiv</a>, <a href="#">D2000 DBManager</a>, <a href="#">D2000 Server</a> )</b> |    |                                                                                                                                                                                                                                                            |
| ODBC_ERROR                                                                                                                                | 34 | ODBC error.                                                                                                                                                                                                                                                |
| <b>Error codes for connection to processes</b>                                                                                            |    |                                                                                                                                                                                                                                                            |
| INVALID_VERSION                                                                                                                           | 30 | Incorrect version.                                                                                                                                                                                                                                         |
| PROCESS_RUN_DISA<br>BLED                                                                                                                  | 31 | Cannot start process.                                                                                                                                                                                                                                      |
| PROCESS_LICENCE_<br>DISABLED                                                                                                              | 32 | Cannot start process - insufficient licence.                                                                                                                                                                                                               |
| PROCESS_TCPIP_DE<br>NIED                                                                                                                  | 33 | Cannot start process - IP address is denied.                                                                                                                                                                                                               |
| <b>Error codes of process <a href="#">D2000 DBManager</a></b>                                                                             |    |                                                                                                                                                                                                                                                            |
| PAGE_ERROR                                                                                                                                | 35 | Page error (in case of page access to database).                                                                                                                                                                                                           |
| EDIT_DISABLED                                                                                                                             | 36 | Editing disabled (when trying to write to a read-only table).                                                                                                                                                                                              |
| DBM_SEQUENCE_ER<br>ROR                                                                                                                    | 37 | <b>DBManager</b> sequence error (invalid object identifier, non-existing transaction, ...)                                                                                                                                                                 |
| DATABASE_OPEN_E<br>RROR                                                                                                                   | 38 | Open database error.                                                                                                                                                                                                                                       |
| BAD_CONDITION                                                                                                                             | 39 | Bad conditions.                                                                                                                                                                                                                                            |
| TOO_MANY_ROWS_I<br>N_SELECT                                                                                                               | 48 | Too many rows in selection (more than specified by the parameter <a href="#">Maximum returned rows</a> in the configuration of object of <a href="#">Database</a> type).                                                                                   |
| DBM_CONNECTION_<br>BROKEN_ERROR                                                                                                           | 49 | Connection with database has been interrupted.                                                                                                                                                                                                             |
| DBM_MAX_CONNECT<br>IONS                                                                                                                   | 50 | Maximum number of connection to the database has been reached (the parameter <a href="#">Maximum connections</a> in the configuration of object of <a href="#">Database</a> type), new connection has not been created.                                    |
| STRUCT_CHANGE                                                                                                                             | 51 | Change of object of <a href="#">Structure definition</a> type in runtime (rows loaded from database do not correspond to the changed object of <a href="#">Structure definition</a> type and are not to be sent to process <a href="#">D2000 Server</a> ). |
| DBM_DATABASE_OFF                                                                                                                          | 52 | Access denied: object of <a href="#">Database</a> type is set to OFF (the parameter <a href="#">Off</a> in the configuration of the object)                                                                                                                |
| <b>Error codes of process <a href="#">D2000 Archiv</a></b>                                                                                |    |                                                                                                                                                                                                                                                            |
| LOAD_TREZOR_ERR<br>OR                                                                                                                     | 40 | Error in loading depository database.                                                                                                                                                                                                                      |
| CREATE_WRT_FILE_<br>ERROR                                                                                                                 | 41 | Create WRT file error when importing Sybase depository database.                                                                                                                                                                                           |
| OPEN_TREZOR_ERR<br>OR                                                                                                                     | 42 | Error in opening depository database.                                                                                                                                                                                                                      |
| CREATE_STATISTICS<br>_ERROR                                                                                                               | 43 | Error in creating statistics file for archive.                                                                                                                                                                                                             |
| <b>Error codes of Tell commands for process <a href="#">D2000 KOM</a></b>                                                                 |    |                                                                                                                                                                                                                                                            |

|                                                                         |    |                                                                                                               |
|-------------------------------------------------------------------------|----|---------------------------------------------------------------------------------------------------------------|
| DUPLICATE_ADDRESS_ERROR                                                 | 44 | Duplicate address (when changing the address of I/O tag by using the Tell command <a href="#">SETPTADDR</a> ) |
| POINT_NOT_FOUND_ERROR                                                   | 45 | I/O tag not found (for Tell command <a href="#">SETPTADDR</a> ).                                              |
| <b>Error codes of process <a href="#">D2000 Application Manager</a></b> |    |                                                                                                               |
| INVALID_DB_PASSWORD                                                     | 47 | Invalid password for access to the configuration database.                                                    |